



Configuring CaseCATalyst Profession/Student Version

CaseCATalyst must be configured to output the realtime English translation to another running program's text input window such as Notepad. EV360 Ultimate's My Realtime and My Games receives the English translation during realtime skill development sessions.

1. With your writer turned on and communicating with your computer, launch Case CATalyst and start a New User you will use with EV360 Ultimate
2. Select Function, then Translate and Edit, or click the Translate Edit icon
 - o for Steno Source, select Writer
 - o for Output Source, select StenoKeys
 - o click the Remember Setting box
3. If you are using EZKeys, deselect this feature. This feature conflicts with the StenoKeys Output Source
4. Create a new file
5. Enter name in File box
6. In the bottom left-hand corner, click Options
 - o select the Output to StenoKeys tab
 - o deselect the Longest match
 - o for Strokes and Seconds enter 0
7. Click OK to exit the Translate Options window
8. Click OK again to exit the Translate window
9. Case CATalyst will open a new file, and search for and connect to your steno writer

The next time you practice with this user, the settings for this user will be saved. To connect, simply click the Translate and Edit icon, select a file, and click OK.

Important: It is important that you disable the audio synchronization feature of the CAT software program. This is a feature where your CAT software will record audio to your computer during a realtime writing session. If you are not sure how to disable audio synchronization, please check your CAT software program's user manual or help feature.